





BUILDING EVACUATION

THE TIME TO BECOME FAMILIAR WITH EMERGENCY PROCEDURES IS BEFORE AN EMERGENCY!

Every department should have a specific **Emergency Evacuation Plan & Assembly Area** where employees, students, and visitors should meet to check in with the supervisor. The OU Police Department or other emergency response personnel should be notified of missing persons so that a search can be made.

EVACUATION PROCEDURES:

- Safely stop your work
- Remain calm and orderly
- Evacuate building immediately if you hear the fire alarm
- If it is safe to do so and does not impede your evacuation, take personal belongings
- If safe to do so, close doors/windows, but do NOT lock them
- Use stairwells
- Assist persons with access & functional needs if possible
- NEVER USE ELEVATORS
- Follow instructions from OU Police or other properly identified emergency personnel
- Go to pre-determined Emergency Assembly Area and report to your supervisor
- Keep all roadways/walkways clear for emergency vehicles
- NEVER RE-ENTER ANY BUILDING until instructed to do so by OU Police or other properly identified emergency personnel

| Name of This Building: | |
|--|--|
| Emergency Assembly Area for this building: | |

Explosions or Severe Building Damage



Protect Yourself During Earthquakes!



CHEMICAL • BIOLOGICAL • RADIOLOGICAL SPILLS

CHEMICAL SPILLS:

- Major spills/assistance/medical treatment, Call/Text: 9-1-1
- Identify/characterize substance(s) involved
- Evacuate if needed
- If safe, remove injured persons
- Questions: contact Environmental Health & Safety Office

CHEMICAL SPILL/SPLASH ON BODY/EYES:

- Know location of eyewash/safety showers near you
- Remove contaminated clothing
- · Brush off remaining dry chemical
- Flush skin/eyes with water for 15 minutes minimum
- Check footwear for accumulation
- ALL splashes in eye(s): seek medical attention

BIOSAFETY LEVEL 1 ORGANISM SPILL:

(low-risk agents for healthy adults)

- Wear disposable gloves
- Place paper towels over spill
- Soak with appropriate disinfectant
- Towel disposal: use plastic bag
- Clean spill area: use fresh towels soaked in disinfectant
- If disinfectant does not completely de-contaminate waste material, autoclave wastes prior to disposal/route for incineration

HUMAN BLOOD OR BIOSAFETY LEVEL 2 ORGANISM SPILL:

(moderate risk agents)

- Alert immediate area of spill
- Put on protective equipment
- Cover spill with paper towels/absorbent materials
- Avoid splashing
- Pour freshly prepared 10 to 1 diluted household bleach or appropriate disinfectant around edges of spill, then into spill
- Allow 20-minute contact period
- After spill is absorbed, clean up spill area with fresh towels soaked in disinfectant
- Place towels in a plastic bag, decontaminate in autoclave/ route for incineration

HUMAN BLOOD OR BIOSAFETY LEVEL 3 ORGANISM: (serious or lethal agents)

- Alert Police, call: 9-1-1
- Do not breathe
- Leave the room immediately
- Close the door
- Notify others in the room to evacuate immediately
- Assist others, if necessary
- Remove personal protective equipment in airlock/access zone
- Turn potentially contaminated clothing outward
- Remove gloves last
- Use antiseptic soap & warm water to wash exposed skin
- Warn others not to enter contaminated area
- Place appropriate sign on door
- Wait minimum 30 minutes for dissipation of aerosols spills
- Coordinate cleanup call: Environmental Health & Safety

RADIOACTIVE MATERIALS SPILL:

- After hours: notify Police, dial: 9-1-1
- Regular hours: report all accidents to Compliance Office
- Notify approved user

®

• If large spill: vacate, do not allow re-entry

PERSONNEL DECONTAMINATION:

- Flush contaminated skin thoroughly with water
- Wash repeatedly with mild soap/warm water
- Lacerated skin by glassware/equipment contaminated with radioactive material: immediately wash wounded area under stream of lukewarm water
- Ingestion radioactive material: report immediately